Intelligent Systems: Reasoning and Recognition

James L. Crowley

ENSIMAG 2 Lesson 2 Winter Semester 2020-2021 5 Feb 2021

Learning and Evaluation for Pattern Recognition

<u>Outline</u>

Notation	2
1. The Pattern Recognition Problem	
Discriminant and Decision Functions	1
Machine Learning	5
Training and Validation ϵ	5
2. Two-Class Pattern Detectors	
3. Performance Metrics for 2 Class Detectors)
ROC Curves)
True Positives and False Positives10)
Precision and Recall11	
F-Measure12	2
Accuracy	2

Notation

X_d	A feature. An observed or measured value.
\vec{X}	A vector of D features.
D	The number of dimensions for the vector \vec{X}
Κ	Number of classes
C_k	The k th class
$\vec{X} \in C_k$	Statement that an observation \vec{X} is a member of class C_k
\hat{C}_k	The estimated class
$D(\vec{X})$	A Recognition (discriminant) function
$\hat{C}_k = D(\vec{X})$	A recognition function that predicts \hat{C}_k from \vec{X}
	For a detection function (K=2), $C_k \in \{P, N\}$
у	The true class for an observation \vec{X}
$\{ec{X}_m\}\ \{y_m\}$	Training samples of \vec{X} for learning, along with ground truth \vec{y}
y_m	An indicator variable (or ground truth) for sample <i>m</i>
M	The number of training samples.

1. The Pattern Recognition Problem

Pattern Recognition is the process of assigning observations to categories. An observation is sometimes called an "entity" or "data" depending on the context and domain.

Observations are produced by some form of sensor. A sensor is a transducer that transforms physical phenomena into digital measurements. These measurements are classically called "Features". We will typically represent features with the variable x.

 $\begin{array}{c|c} \mathsf{External} & \longrightarrow & \mathsf{Sensor} \\ \mathsf{World} & \longrightarrow & \vec{X} \end{array}$

Features may be Boolean, natural numbers, integers, real numbers or symbolic labels.

In most interesting problems, the sensor provides a feature vector, \vec{X} , composed of D

properties or features

$$\vec{X} = \begin{pmatrix} x_1 \\ x_2 \\ \vdots \\ x_D \end{pmatrix}$$

Our problem is to build a function, called a recognizer or classifier, $D(\vec{X})$, that maps the observation, \vec{X} into a statement that the observation belongs to a class \hat{C}_k from a set of K possible classes. $D(\vec{X}) \rightarrow \hat{C}_k$

$$\vec{X} \longrightarrow D(\vec{X}) \longrightarrow \hat{C}_k$$

In most classic techniques, the class \hat{C}_k is from a set of K known classes $\{C_k\}$. For a 2-class detection function, there are K=2 classes : k=1 is a positive detection P, k=2 is a negative detection, N. Thus $C_k \in \{P,N\}$

Almost all current classification techniques require the number of classes, K, to be fixed. ($\{C_k\}$ is a closed set). An interesting research problem is how to design classification algorithms that allow $\{C_k\}$ to be an open set that grows with experience.

Discriminant and Decision Functions

The classification function $D(\vec{X})$ can typically be decomposed into two parts:

$$\hat{C}_k \leftarrow D(\vec{X}) = d\left(\vec{g}\left(\vec{X}\right)\right)$$

where $\vec{g}(\vec{X})$ is a discriminant function and $d(\vec{g}(\vec{X}))$ is a decision function.

 $\vec{g}(\vec{X}): \vec{X} \to \mathbb{R}^{K}$ A discriminant function that maps features to discriminants

 $d(\vec{g}(\vec{X})): \mathbb{R}^{K} \to \hat{C}_{k} \in \{C_{k}\}$ A decision function that maps discriminants to a class (or an ordered list of classes).

The discriminant is typically a vector of functions, with one for each class.

$$\vec{g}(\vec{X}) = \begin{pmatrix} g_1(\vec{X}) \\ g_2(\vec{X}) \\ \vdots \\ g_K(\vec{X}) \end{pmatrix}$$

The decision function, $d(\vec{g}(\vec{X}))$, can be arg-max{}, a logistics sigmoid function, or any other function that selects or rankes C_k from $\vec{g}(\vec{X})$.

A common choice is arg-max{}.

$$\hat{C}_k = d(\vec{g}(\vec{X})) = \arg - \max_{C_k} \{g_k(\vec{X})\}$$

In some problems, there is a notion of "cost" for errors that the cost is different for different decisions. In this case we will seek to minimize the cost of an error rather than the number of errors by biasing the classification with a notion of risk.

Machine Learning

Machine learning explores the study and construction of algorithms that can learn from and make predictions about data. Learning for Pattern Recognition is only one of many forms of machine learning. Over the last 50 years, many techniques for machine learning have been developed for many different applications, each with its own advantages and disadvantages.

For pattern recognition, the common approach is to a set of "training data" to estimate the discriminant function $\vec{g}(\vec{X})$.

The danger is that the discriminant function may not generalize to data outside the training set. The quality of the recognizer depends on the degree to which the training data $\{\vec{X}_m\}$ represents the range of variations of real data.

Supervised Learning

Most classical methods for machine learning for recognition estimate a discriminant function a set of labeled training data, composed of *M* independent examples, $\{\vec{X}_m\}$ for which we know the true class $\{y_m\}$.

The set $\{\vec{X}_m\}$ is called the training data. The set $\{y_m\}$ are the indicator variables.

Having the true class $\{y_m\}$ makes it much easier to estimate the functions $g_k(\vec{X})$. Most of the technique that we will see will use supervised learning.

Semi-Supervised Learning.

A number of hybrid algorithms exist that initiate learning from a labeled training set and then extend the learning with unlabeled data.

Unsupervised Learning

Unsupervised Learning techniques learn the recognition function without a labeled training set. Such methods typically require a much larger sample of data for learning.

In most learning algorithms, we partition the training data in distinct sets in order to estimate the recognizer and to evaluate the results. A FUNDAMENTAL RULE in machine learning:

NEVER LEARN AND TEST WITH THE SAME DATA !

A typical approach is to use cross validation (also known as rotation estimation) in learning. Cross validation partitions the training data into N folds (or complementary subsets). A subset of the folds are used to train the classifier, and the result is tested on the other folds. A taxonomy of common techniques include:

- Exhaustive cross-validation
 - Leave p-out cross-validation
 - Leave one-out cross-validation
- Non-exhaustive cross-validation
 - k-fold cross-validation
 - o 2-fold cross-validation
 - Repeated sub-sampling validation

When training neural networks, we will generally divide the data into three sets:

Training Set - used to train the discriminant functions

Evaluation Set - Used to monitor learning and avoid overfitting to the training set Test Set - used to evaluate the final result and compare different techniques and architectures.

2. Two-Class Pattern Detectors

A pattern detector is a classifier or recognizer with K=2.

Class k=1: The target pattern, also known as P or positive

Class k=2: Everything else, also known as N or negative.

Pattern detectors are used in computer vision, for example to detect faces, road signs, publicity logos, or other patterns of interest. They are also used in signal communications, data mining and many other domains.

The pattern detector is learned as a detection function $g(\vec{x})$ followed by a decision rule, d(). For K=2 this can be reduced to a single function, as

 $g_1(\vec{X}) \ge g_2(\vec{X})$ is equivalent to $g(\vec{X}) = g_1(\vec{X}) - g_2(\vec{X}) \ge 0$

A "threshold" value, B, can be used to bias the detector.

The detection function is learned from a set of training data composed of *M* sample observations $\{\vec{X}_m\}$ where each sample observation is labeled with an indicator variable $\{y_m\}$

 $y_m = P$ or Positive for examples of the target pattern (class k=1)

 y_m = N or Negative for all other examples (class k=2)

Observations for which $g(\vec{X}) + B \ge 0$ are estimated to be members of the target class. This will be called POSITIVE or P.

Observations for which $g(\vec{X}) + B < 0$ are estimated to be members of the background. This will be called NEGATIVE or N.

We can encode this as a decision function to define our detection function $R(\vec{X}_m)$

$$D(\vec{X}) = d(g(\vec{X})) = \begin{cases} P & \text{if } g(\vec{X}) + B \ge 0\\ N & \text{if } g(\vec{X}) + B < 0 \end{cases}$$

For training we need ground truth (annotation). For each training sample the annotation or ground truth tells us the real class y_m

 $y_m = \begin{cases} P & \vec{X}_m \in \text{Target - Class} \\ N & \text{otherwise} \end{cases}$

2-7

The Classification can be TRUE or FALSE.

if $D(\vec{X}_m) = y_m$ then T else F

This gives

 $D(\vec{X}_m) = y_m$ AND $D(\vec{X}_m) = P$ is a TRUE POSITIVE or TP $D(\vec{X}_m) \neq y_m$ AND $D(\vec{X}_m) = P$ is a FALSE POSITIVE or FP $D(\vec{X}_m) \neq y_m$ AND $D(\vec{X}_m) = N$ is a FALSE NEGATIVE or FN $D(\vec{X}_m) = y_m$ AND $D(\vec{X}_m) = N$ is a TRUE NEGATIVE or TN

To better understand the detector we need a tool to explore the trade-off between making false detections (false positives) and missed detections (false negatives). The Receiver Operating Characteristic (ROC) provides such a tool

3. Performance Metrics for 2 Class Detectors

A number of performance metrics are commonly used to compare 2-class classifiers. These can be extended to multi-class detectors by using "one vs many".

That is, the detector for each class, C_k , is evaluated individually by labeling C_k as the target or Positive (P) class and all other classes as the non-target or Negative (N) class.

ROC Curves

Two-class classifiers have long been used for signal detection problems in communications and have been used to demonstrate optimality for signal detection methods. The quality metric that is used is the Receiver Operating Characteristic (ROC) curve. This curve can be used to describe or compare any method for signal or pattern detection.

The ROC curve is generated by adding a variable Bias term to a discriminant function.

 $D(\vec{X}) = d(g(\vec{X}) + B)$

and plotting the rate of true positive detection vs false positive detection.

As the bias term, B, is swept through a range of values, it changes the ratio of true positive detection to false positives.

When $B \ll 0$ all detections will be Negative. When $B \gg 0$ all detections will be Positive. For some range of values of B, $D(\vec{X})$ will give a mix of TP, TN, FP and FN.

The bias term, B, can act as an adjustable gain that sets the sensitivity of the detector. The bias term allows us to trade False Positives for False Negatives.

The resulting curve is called a Receiver Operating Characteristics (ROC) curve. The ROC plots True Positive Rate (TPR) against False Positive Rate (FPR) as a function of B for the training data $\{\vec{X}_m\}, \{y_m\}$.

Lesson 2

True Positives and False Positives

For each training sample, the detection as either Positive (P) or Negative (N)

IF $g(\vec{X}_m) + B \ge 0$ THEN P else N

The detection can be TRUE (T) or FALSE (F) depending on the indicator variable y_m

IF $y_m = D(\vec{X}_m)$ THEN T else F

Combining these two values, any detection can be a True Positive (TP), False Positive (FP), True Negative (TN) or False Negative (FN).

For the M samples of the training data $\{\vec{X}_m\}$, $\{y_m\}$ we can define:

#P as the number of Positives in the training data.

#N as the number of Negatives in the training data.

#T as the number of training samples correctly labeled by the detector.

#F as the number of training samples incorrectly labeled by the detector. From this we can define:


#TP as the number of training samples correctly labeled as Positive #FP as the number of training samples incorrectly labeled as Positive #TN as the number of training samples correctly labeled as Negative #FN as the number of training samples incorrectly labeled as Negative

Note that #P = #TP + #FN (positives in the training data) And #N = #FP + #TN (negatives in the training data)

The True Positive Rate (TPR) is $TPR = \frac{\#TP}{\#P} = \frac{\#TP}{\#TP + \#FN}$

The False Positive Rate (FPR) is $FPR = \frac{\#FP}{\#N} = \frac{\#FP}{\#FP + \#TN}$

The ROC plots the TPR against the FPR as a bias B is swept through a range of values.



When B is at its minimum, all the samples are detected as N, and both the TPR and FPR are 0. As B increases both the TPR and FPR increase. Normally TPR should rise monotonically with FPR. If TPR and FPR are equal, then the detector is no better than chance.

The closer the curve approaches the upper left corner, the better the detector.

	$y_m = D(\vec{X}_m)$	$y_m \neq D(\vec{X}_m)$
$d(g(\vec{X}_m) + B \ge 0)$	True Positive (TP)	False Positive (FP)
$d(g(\vec{X}_m) + B < 0)$	True Negative (TN)	False Negative (FN)

Precision and Recall

Precision, also called Positive Predictive Value (PPV), is the fraction of retrieved instances that are relevant to the problem.

$$PP = \frac{TP}{TP + FP}$$

A perfect precision score (PPV=1.0) means that every result retrieved by a search was relevant, but says nothing about whether all relevant documents were retrieved.

Recall, also known as sensitivity (S), hit rate, and True Positive Rate (TPR) is the fraction of relevant instances that are retrieved.

$$S = TPR = \frac{TP}{P} = \frac{TP}{TP + FN}$$

A perfect recall score (TPR=1.0) means that all relevant documents were retrieved by the search, but says nothing about how many irrelevant documents were also retrieved.

Both precision and recall are therefore based on an understanding and measure of relevance. In our case, "relevance" corresponds to "True".

Precision answers the question "How many of the Positive Elements are True ?" Recall answers the question "How many of the True elements are Positive"?


In many domains, there is an inverse relationship between precision and recall. It is possible to increase one at the cost of reducing the other.

F-Measure

The F-measures combine precision and recall into a single value. The F measures measure the effectiveness of retrieval. The best value is 1 when Precision and Recall are perfect. The worst value is at Zero.

The F_1 score weights recall higher than precision.

F₁ Score:



The F1 score is the harmonic mean of precision and recall.

Accuracy

Accuracy is the fraction of test cases that are correctly classified (T).

$$ACC = \frac{T}{M} = \frac{TP + TN}{M}$$

where M is the quantity of test data.

Note that the terms Accuracy and Precision have a very different meaning in Measurement theory. In measurement theory, accuracy is the average distance from a true value, while precision is a measure of the reproducibility for the measurement.